

NAG Library Function Document

nag_1d_quad_wt_trig_1 (d01snc)

1 Purpose

nag_1d_quad_wt_trig_1 (d01snc) calculates an approximation to the sine or the cosine transform of a function g over $[a, b]$:

$$I = \int_a^b g(x) \sin(\omega x) dx \quad \text{or} \quad I = \int_a^b g(x) \cos(\omega x) dx$$

(for a user-specified value of ω).

2 Specification

```
#include <nag.h>
#include <nagd01.h>
void nag_1d_quad_wt_trig_1 (
    double (*g)(double x, Nag_User *comm),
    double a, double b, double omega, Nag_TrigTransform wt_func,
    double epsabs, double epsrel, Integer max_num_subint, double *result,
    double *abserr, Nag_QuadProgress *qp, Nag_User *comm, NagError *fail)
```

3 Description

nag_1d_quad_wt_trig_1 (d01snc) is based upon the QUADPACK routine QFOUR (Piessens *et al.* (1983)). It is an adaptive function, designed to integrate a function of the form $g(x)w(x)$, where $w(x)$ is either $\sin(\omega x)$ or $\cos(\omega x)$. If a sub-interval has length

$$L = |b - a|2^{-l}$$

then the integration over this sub-interval is performed by means of a modified Clenshaw–Curtis procedure (Piessens and Branders (1975)) if $L\omega > 4$ and $l \leq 20$. In this case a Chebyshev series approximation of degree 24 is used to approximate $g(x)$, while an error estimate is computed from this approximation together with that obtained using Chebyshev series of degree 12. If the above conditions do not hold then Gauss 7-point and Kronrod 15-point rules are used. The algorithm, described in Piessens *et al.* (1983), incorporates a global acceptance criterion (as defined in Malcolm and Simpson (1976)) together with the ϵ -algorithm (Wynn (1956)) to perform extrapolation. The local error estimation is described in Piessens *et al.* (1983).

4 References

- Malcolm M A and Simpson R B (1976) Local versus global strategies for adaptive quadrature *ACM Trans. Math. Software* **1** 129–146
- Piessens R and Branders M (1975) Algorithm 002: computation of oscillating integrals *J. Comput. Appl. Math.* **1** 153–164
- Piessens R, de Doncker–Kapenga E, Überhuber C and Kahaner D (1983) *QUADPACK, A Subroutine Package for Automatic Integration* Springer–Verlag
- Wynn P (1956) On a device for computing the $e_m(S_n)$ transformation *Math. Tables Aids Comput.* **10** 91–96

5 Arguments

- 1: **g** – function, supplied by the user *External Function*
g must return the value of the function g at a given point.
- The specification of **g** is:

```
double g (double x, Nag_User *comm)
```

1: **x** – double *Input*
On entry: the point at which the function g must be evaluated.

2: **comm** – Nag_User *
 Pointer to a structure of type Nag_User with the following member:
p – Pointer
On entry/exit: the pointer **comm**→**p** should be cast to the required type, e.g.,
`struct user *s = (struct user *)comm → p;`, to obtain the original
object's address with appropriate type. (See the argument **comm** below.)
- 2: **a** – double *Input*
On entry: the lower limit of integration, a .
- 3: **b** – double *Input*
On entry: the upper limit of integration, b . It is not necessary that $a < b$.
- 4: **omegap** – double *Input*
On entry: the argument ω in the weight function of the transform.
- 5: **wt_func** – Nag_TrigTransform *Input*
On entry: indicates which integral is to be computed:
if **wt_func** = Nag_Cosine, $w(x) = \cos(\omega x)$;
if **wt_func** = Nag_Sine, $w(x) = \sin(\omega x)$.
Constraint: **wt_func** = Nag_Cosine or Nag_Sine.
- 6: **epsabs** – double *Input*
On entry: the absolute accuracy required. If **epsabs** is negative, the absolute value is used. See Section 7.
- 7: **epsrel** – double *Input*
On entry: the relative accuracy required. If **epsrel** is negative, the absolute value is used. See Section 7.
- 8: **max_num_subint** – Integer *Input*
On entry: the upper bound on the number of sub-intervals into which the interval of integration may be divided by the function. The more difficult the integrand, the larger **max_num_subint** should be.
Constraint: **max_num_subint** ≥ 1 .

9:	result – double *	<i>Output</i>
<i>On exit:</i> the approximation to the integral I .		
10:	abserr – double *	<i>Output</i>
<i>On exit:</i> an estimate of the modulus of the absolute error, which should be an upper bound for $ I - \text{result} $.		
11:	qp – Nag_QuadProgress *	
Pointer to structure of type Nag_QuadProgress with the following members:		
	num_subint – Integer	<i>Output</i>
	<i>On exit:</i> the actual number of sub-intervals used.	
	fun_count – Integer	<i>Output</i>
	<i>On exit:</i> the number of function evaluations performed by nag_1d_quad_wt_trig_1 (d01snc).	
	sub_int_beg_pts – double *	<i>Output</i>
	sub_int_end_pts – double *	<i>Output</i>
	sub_int_result – double *	<i>Output</i>
	sub_int_error – double *	<i>Output</i>
	<i>On exit:</i> these pointers are allocated memory internally with max_num_subint elements. If an error exit other than NE_INT_ARG_LT, NE_BAD_PARAM or NE_ALLOC_FAIL occurs, these arrays will contain information which may be useful. For details, see Section 9.	
	Before a subsequent call to nag_1d_quad_wt_trig_1 (d01snc) is made, or when the information contained in these arrays is no longer useful, you should free the storage allocated by these pointers using the NAG macro NAG_FREE.	
12:	comm – Nag_User *	
Pointer to a structure of type Nag_User with the following member:		
	p – Pointer	
	<i>On entry/exit:</i> the pointer comm – p , of type Pointer, allows you to communicate information to and from g(). An object of the required type should be declared, e.g., a structure, and its address assigned to the pointer comm – p by means of a cast to Pointer in the calling program, e.g., comm.p = (Pointer)& s . The type Pointer is void *.	
13:	fail – NagError *	<i>Input/Output</i>
The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).		

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.

NE_BAD_PARAM

On entry, argument **wt_func** had an illegal value.

NE_INT_ARG_LT

On entry, **max_num_subint** must not be less than 1: **max_num_subint** = *<value>*.

NE_QUAD_BAD_SUBDIV

Extremely bad integrand behaviour occurs around the sub-interval $(\langle value \rangle, \langle value \rangle)$.
The same advice applies as in the case of NE_QUAD_MAX_SUBDIV.

NE_QUAD_MAX_SUBDIV

The maximum number of subdivisions has been reached: **max_num_subint** = $\langle value \rangle$.

The maximum number of subdivisions has been reached without the accuracy requirements being achieved. Look at the integrand in order to determine the integration difficulties. If the position of a local difficulty within the interval can be determined (e.g., a singularity of the integrand or its derivative, a peak, a discontinuity, etc.) you will probably gain from splitting up the interval at this point and calling the integrator on the sub-intervals. If necessary, another integrator, which is designed for handling the type of difficulty involved, must be used. Alternatively, consider relaxing the accuracy requirements specified by **epsabs** and **epsrel**, or increasing the value of **max_num_subint**.

NE_QUAD_NO_CONV

The integral is probably divergent or slowly convergent.

Please note that divergence can also occur with any error exit other than NE_INT_ARG_LT, NE_BAD_PARAM or NE_ALLOC_FAIL.

NE_QUAD_ROUND OFF_EXTRAPL

Round-off error is detected during extrapolation.

The requested tolerance cannot be achieved, because the extrapolation does not increase the accuracy satisfactorily; the returned result is the best that can be obtained.

The same advice applies as in the case of NE_QUAD_MAX_SUBDIV.

NE_QUAD_ROUND OFF_TOL

Round-off error prevents the requested tolerance from being achieved: **epsabs** = $\langle value \rangle$, **epsrel** = $\langle value \rangle$.

The error may be underestimated. Consider relaxing the accuracy requirements specified by **epsabs** and **epsrel**.

7 Accuracy

`nag_1d_quad_wt_trig_1` (d01snc) cannot guarantee, but in practice usually achieves, the following accuracy:

$$|I - \text{result}| \leq tol$$

where

$$tol = \max\{|\text{epsabs}|, |\text{epsrel}| \times |I|\}$$

and **epsabs** and **epsrel** are user-specified absolute and relative error tolerances. Moreover it returns the quantity **abserr** which, in normal circumstances, satisfies

$$|I - \text{result}| \leq \text{abserr} \leq tol.$$

8 Parallelism and Performance

`nag_1d_quad_wt_trig_1` (d01snc) is not threaded in any implementation.

9 Further Comments

The time taken by `tnag_1d_quad_wt_trig_1` (d01snc) depends on the integrand and the accuracy required.

If the function fails with an error exit other than NE_INT_ARG_LT, NE_BAD_PARAM or NE_ALLOC_FAIL, then you may wish to examine the contents of the structure **qp**. These contain the end-points of the sub-intervals used by nag_1d_quad_wt_trig_1 (d01snc) along with the integral contributions and error estimates over the sub-intervals.

Specifically, $i = 1, 2, \dots, n$, let r_i denote the approximation to the value of the integral over the sub-interval $[a_i, b_i]$ in the partition of $[a, b]$ and e_i be the corresponding absolute error estimate.

Then, $\int_{a_i}^{b_i} g(x)w(x)dx \simeq r_i$ and **result** = $\sum_{i=1}^n r_i$ unless the function terminates while testing for divergence of the integral (see Section 3.4.3 of Piessens *et al.* (1983)). In this case, **result** (and **abserr**) are taken to be the values returned from the extrapolation process. The value of n is returned in **qp**→**num_subint**, and the values a_i , b_i , r_i and e_i are stored in the structure **qp** as

$$\begin{aligned} a_i &= \mathbf{qp} \rightarrow \mathbf{sub_int_beg_pts}[i - 1], \\ b_i &= \mathbf{qp} \rightarrow \mathbf{sub_int_end_pts}[i - 1], \\ r_i &= \mathbf{qp} \rightarrow \mathbf{sub_int_result}[i - 1] \text{ and} \\ e_i &= \mathbf{qp} \rightarrow \mathbf{sub_int_error}[i - 1]. \end{aligned}$$

10 Example

This example computes

$$\int_0^1 \ln x \sin(10\pi x) dx.$$

10.1 Program Text

```
/* nag_1d_quad_wt_trig_1 (d01snc) Example Program.
*
* NAGPRODCODE Version.
*
* Copyright 2016 Numerical Algorithms Group.
*
* Mark 26, 2016.
*/
*/

#include <nag.h>
#include <stdio.h>
#include <nag_stdl�.h>
#include <math.h>
#include <nagd01.h>
#include <nagx01.h>

#ifndef __cplusplus
extern "C"
{
#endif
static double NAG_CALL g(double x, Nag_User *comm);
#ifndef __cplusplus
}
#endif

int main(void)
{
    static Integer use_comm[1] = { 1 };
    Integer exit_status = 0;
    double a, b;
    double omega;
    double epsabs, abserr, epsrel, result;
    Nag_TrigTransform wt_func;
    Nag_QuadProgress qp;
    Integer max_num_subint;
    NagError fail;
    Nag_User comm;
```

```

INIT_FAIL(fail);

printf("nag_1d_quad_wt_trig_1 (d01snc) Example Program Results\n");

/* For communication with user-supplied functions: */
comm.p = (Pointer) &use_comm;

epsrel = 0.0001;
epsabs = 0.0;
a = 0.0;
b = 1.0;
/* nag_pi (x01aac).
 * pi
 */
omega = nag_pi * 10.0;
wt_func = Nag_Sine;
max_num_subint = 200;
/* nag_1d_quad_wt_trig_1 (d01snc).
 * One-dimensional adaptive quadrature, finite interval,
 * sine or cosine weight functions, thread-safe
 */
nag_1d_quad_wt_trig_1(g, a, b, omega, wt_func, epsabs, epsrel,
                      max_num_subint, &result, &abserr, &qp, &comm, &fail);
printf("a      - lower limit of integration = %10.4f\n", a);
printf("b      - upper limit of integration = %10.4f\n", b);
printf("epsabs - absolute accuracy requested = %11.2e\n", epsabs);
printf("epsrel - relative accuracy requested = %11.2e\n\n", epsrel);
if (fail.code != NE_NOERROR)
    printf("Error from nag_1d_quad_wt_trig_1 (d01snc) %s\n", fail.message);
if (fail.code != NE_INT_ARG_LT && fail.code != NE_BAD_PARAM &&
    fail.code != NE_ALLOC_FAIL && fail.code != NE_NO_LICENCE) {
    printf("result - approximation to the integral = %9.5f\n", result);
    printf("abserr - estimate of the absolute error = %11.2e\n", abserr);
    printf("qp.fun_count - number of function evaluations = %4" NAG_IFMT
          "\n", qp.fun_count);
    printf("qp.num_subint - number of subintervals used = %4" NAG_IFMT "\n",
          qp.num_subint);
    /* Free memory used by qp */
    NAG_FREE(qp.sub_int_beg_pts);
    NAG_FREE(qp.sub_int_end_pts);
    NAG_FREE(qp.sub_int_result);
    NAG_FREE(qp.sub_int_error);
}
else {
    exit_status = 1;
    goto END;
}

END:
    return exit_status;
}

static double NAG_CALL g(double x, Nag_User *comm)
{
    Integer *use_comm = (Integer *) comm->p;

    if (use_comm[0]) {
        printf("(User-supplied callback g, first invocation.)\n");
        use_comm[0] = 0;
    }

    return (x > 0.0) ? log(x) : 0.0;
}

```

10.2 Program Data

None.

10.3 Program Results

```
nag_1d_quad_wt_trig_1 (d01snc) Example Program Results
(User-supplied callback g, first invocation.)
a      - lower limit of integration =    0.0000
b      - upper limit of integration =   1.0000
epsabs - absolute accuracy requested =  0.00e+00
epsrel - relative accuracy requested =  1.00e-04

result - approximation to the integral = -0.12814
aberr - estimate of the absolute error =  3.58e-06
qp.fun_count - number of function evaluations = 275
qp.num_subint - number of subintervals used =    8
```
